Broadworks Anywhere

FUSIONWORKS QUICK GUIDE


Making a Call

- Once you have added your numbers, to use the Broadworks Anywhere feature, call any of the Broadworks Anywhere Portal numbers.
- 2. The system will answer with a greeting that says, "Enter the destination digits". You will then hear a dial tone.
- At the dial tone, enter the destination number. The system will call it and display your office number as the calling name/ number not the number of the device you are actually calling from.

TIP: To see the available Portal numbers that you can use, click the **View Available Portal List** link from the Main page.

BroadWorks Anywhere

Configure the fixed and mobile phones you would like to link to this



The Numbers will appear here.

Available BroadWorks Anywhere Portals

Lists all the available BroadWorks Anywhere portals for the user.


Portal Name	Phone Number	Extension	Language
2063404631	+12063404631	4631	English
4042317255	+14042317255	7255	English
4049904987	+14049904987	4987	English

Pull an Active Call from VVX to Cell Phone

- 1. While on an active call, dial your Broadworks Anywhere access number from your cell phone.
- 2. Enter *11.
- 3. The call has now moved to your cell phone.
- To move the call back to your VVX deskphone, enter *11 on your VVX.
- 5. The call has moved back to your VVX.



f C in 🤁 🖉





Broadworks Anywhere

The **Broadworks Anywhere** feature allows you to make outbound calls from any number by first dialing the Broadworks Anywhere Portal Number and then entering the destination number. This will display your office number as the Caller ID to the called party and will bill the Long Distance charge, if any to the Firm.

Contact Phone System Administrator for Access Number

To use the Broadworks Anywhere feature you must first add any numbers you will be calling from to the system as known numbers. If you do not, the system will not recognize them and will not allow you to use the feature.


To add your numbers (home, cell, etc.) to the system:

- 1. Open your PC's browser and navigate to: http://voiceadmin.fusionconnect.com
- 2. Enter your 10 Digit User ID and Password.
- 3. Click **Call Control** in the left hand menu.

fusion

	Profile
	A CONTRACTOR OF CONTRACTOR OFO
	Incoming Calls
	Outgoing Calls
1	Call Control
	Calling Plans
	Client Applications

4. From the Call Control page, click the Broadworks Anywhere link.



Adding New Numbers

1. To add a new number, click the Add Button.

BroadWorks Anywhere

Configure the fixed and mobile phones you would like to link to this account.



2. Enter the phone number and a name for this number as shown on this example.

BroadWorks Anywhere Phone Number Add

Allows BroadWorks Anywhere Phone Number to be configured along with multiple selective criteria for ea

Phone Number			Selective Criteria	Selective Criteria		
		Phone Number:	555-555-5555			
		Description: Cell Phone				
			Enable this Location			

 Remove the check box next to Enable this Location. If you leave the check box on Enable this Location, the system will simultaneously ring this number each time you receive a call to your office number.

BroadWorks Anywhere Phone Number Add

Allows BroadWorks Anywhere Phone Number to be configured along with multiple selective

Phone	Number			Selective Crite	eria
			- Office		
	* F	hone Numb	er: 555-555-55	555	
		Descriptio	n: Cell Phone	9	
			Enable this	Location	

- 4. Leave all other boxes/fields blank.
- 5. To save, click the OK Button.
- 6. Repeat these steps to add additional numbers.